

Product Change Notice

Product Model Name: UDO30

Date: January 28, 2008

Reference ECO No: 18840

Reason for Change

This PCN announces the release of UDO30 drive firmware version U06. This firmware is available at no cost from Plasmon via the website, www.plasmontech.com.

Description of Change

The following changes/features are incorporated into the new firmware release:

- A change was made to eliminate an invalid Blank Check (08-93-00) being reported during a successful read.
- A change was made to clear the calibration log after using the cleaning cartridge. The drive would not recalibrate a disk that was recognized in the calibration log if the temperature of the drive was within 5 degrees C of its last calibration. All disks will be recalibrated and added to the calibration log after a cleaning operation.

Firmware

To confirm the current firmware version, issue an Inquiry (12H) command.

The following table shows the release history of the UDO30 firmware:

Code	Release Date	ECO#
U01	August 2004	16495
U02	November 2004	16656
U03	September 2005	17167
U04 (recalled)	January 2006	17454
U04a	February 2006	17508
U05	April 2006	17629
U05A	August 2007	18630
U06	January	18840

Caution: Do not attempt to install an earlier revision of UDO drive firmware on newer hardware. Downgrading UDO firmware can lead to uncertain and unsupported consequences.

Contact Information for Technical Questions:

Americas and Asia Pacific

Plasmon Technical Support Team
United States Calls: 1-877-585-6793
International Calls: 1-719-593-4437
Fax: 1-719-593-4192
Email: tech.support@plasmon.com
Internet: www.plasmon.com

Europe, Africa, and Middle East

Plasmon Technical Support Team
International Calls: +44 (0) 1763 262 963
Fax: +44 (0) 1763 264 407
Email: support@plasmon.co.uk
Internet: www.plasmon.com