

# Product Change Notice

**Product Model Name: Gx134 – Gx174**

**Date: April 2008**

**Reference ECO No: 18904**

## Reason for Change

This PCN announces the release of G134 – G174 library firmware version H06e. This firmware is available at no cost from Plasmon via the website [www.plasmontech.com](http://www.plasmontech.com).

## Description of Change

The following changes/features are incorporated into the new firmware release:

- Resolved the intermittent interference of the picker finger at the drive bezel during the error recovery process.
- The LOG SELECT error statistics page , 31H, will now clear as denoted by the SCSI specification.
- UDO2 drive cleaning capability added to maintenance menu.
- H06c introduced an erroneous error of 04-80-20 at the end of the LIB VERIFY test. The erroneous error is resolved.
- Increased the put force of the picker at the drive to alleviate the occurrence of stalled pickers which caused library recoveries.

## Firmware

To confirm the current firmware version using the front panel display menus, select menu 1 Library Status > 1 Config Information > 1 Unit Information. If the new firmware is installed the front panel displays: **H06B CPU = 3069, DSP = 3046, CPLD = 0004** in bold text.

The following table shows the release history of the G134 – G174 library firmware.

| Code | ECO#  | CPU  | DSP  | CPLD       |
|------|-------|------|------|------------|
| H03  | 17044 | 3038 | 3032 | Up to 0003 |
| H04  | 17185 | 3040 | 3034 | Up to 0003 |
| H04a | 17241 | 3046 | 3034 | Up to 0003 |
| H05a | 17636 | 3053 | 3039 | Up to 0004 |
| H05d | 17925 | 3056 | 3041 | Up to 0004 |
| H05e | 18053 | 3057 | 3041 | Up to 0004 |
| H05f | 18092 | 3058 | 3041 | Up to 0004 |
| H06  | 18460 | 3060 | 3043 | Up to 0004 |
| H06b | 18571 | 3064 | 3043 | Up to 0004 |
| H06c | 18750 | 3065 | 3043 | Up to 0004 |
| H06e | 18904 | 3069 | 3046 | Up to 0004 |

**Contact Information for Technical Questions:**

**Americas and Asia Pacific**

Plasmon Technical Support Team  
United States Calls: 1-877-585-6793  
International Calls: 1-719-593-4437  
Fax: 1-719-593-4192  
Email: [tech.support@plasmon.com](mailto:tech.support@plasmon.com)  
Internet: [www.plasmon.com](http://www.plasmon.com)

**Europe, Africa, and Middle East**

Plasmon Technical Support Team  
International Calls: +44 (0) 1763 262 963  
Fax: +44 (0) 1763 264 407  
Email: [support@plasmon.co.uk](mailto:support@plasmon.co.uk)  
Internet: [www.plasmon.com](http://www.plasmon.com)